


# ***RFeditor***

## User Guide v3.7.x



Xiaotao Yang\*, Gary Pavlis, Yinzhi Wang

Indiana University

July 2018

---

\* Now at University of Massachusetts Amherst, [xiaotaoyang@umass.edu](mailto:xiaotaoyang@umass.edu).

## Table of Content

<b>Table of Content</b> .....	i
<b>1. Introduction</b> .....	1
1.1 Download .....	1
1.2 Citation.....	1
1.3 Support.....	1
<b>2. Installation</b> .....	2
2.1 Operation Systems .....	2
2.2 Library dependency .....	2
2.3 Install <i>RFeditor</i> .....	4
<b>3. Command Line Options</b> .....	5
<b>4. Parameter File</b> .....	6
4.1 Global parameters driving the program .....	6
4.2 Parameters driving the QC in GUI-mode .....	8
4.3 Parameters driving the QC in Auto-mode .....	9
4.4 Other optional parameters .....	11
4.4.1 First arrival detection.....	11
4.4.2 Metadata lists for input and output tables.....	12
4.4.3 Keys of the deconvolution attributes .....	12
4.4.4 Plotting window parameters.....	12
<b>5. Data Preparation</b> .....	15
<b>5.1 Data for deconvolution</b> .....	15
<b>6. QC in GUI-Mode</b> .....	16
<b>6.1 Mouse operation conventions</b> .....	17
<b>6.2 Menus in the tool bar</b> .....	17
<b>7. QC in Auto-Mode</b> .....	23
<b>References</b> .....	24

## 1. Introduction

In this file, we use the symbol ‘\$command’ to denote terminal inputs. We use \$ANTELOPE to denote for the Antelope root path on your computer. We refer the path where you store the RFeditor source package to be RFEROOT.

### 1.1 Download

The package is available at: <https://github.com/xyangpsp/RFeditor>. You can get the package by running in the terminal under the directory where you would like to save the code:

```
git clone https://github.com/xyangpsp/RFeditor.git .
```

Assuming you have downloaded the package and saved it to: /Users/myhome/SOFT/src/RFeditor, this path is referred to as RFEROOT in this user guide. Under this directory, there are four subfolders:

#### (1) libtreditoperator

This directory contains the lib needed by RFeditor editing procedures. However, the library files are currently embedded in RFeditor core codes. Thus, compiling RFeditor does not require the compiling of this library. This library can be used by other utilities or extensional programs.

#### (2) RFeditor\_core

This folder contains the RFeditor core source code. The source code for the required library libseisw.a is also included under libseisw.

#### (3) Utilities

This folder includes the utilities related to the use of RFeditor.

#### (4) Docs

This folder contains this user guide and other related materials.

#### (5) RFeditor\_demo\_portable.zip

This data set should be used for testing purpose ONLY after the program is successfully installed. Please don't use the data for research purpose. Accuracy of the data is NOT guaranteed.

### 1.2 Citation

Reference for the method: Yang, X. T., G. L. Pavlis, and Y. Wang (2016), A quality control method for teleseismic P-wave receiver functions, *Bull. Seismol. Soc. Am.*, 106(5), 1948–1962, doi:10.1785/0120150347.

### 1.3 Support

Support is provided through GitHub platform. You can create an issue or ask questions at: <https://github.com/xyangpsp/RFeditor>. Or you can send emails regarding questions to: [xyang@indiana.edu](mailto:xyang@indiana.edu).

## 2. Installation

This program operates based on an Antelope Datascope database (version 5.5 and later). Go to: <http://www.antelopeusersgroup.org> to install `contrib` following the procedures there, if it is not installed along with the Antelope package. Please make sure that Antelope is working properly before installing this program. If you downloaded and installed the `contrib` package through `git` repository, you can update it, under your `$ANTELOPE/contrib`, by typing in terminal:

```
$ git pull
```

This will update your `contrib` package. After it finishes, recompile the updated programs. In Antelope 5.7, the `contrib` package is automatically downloaded into `/opt/antelope/src`. You can then copy or create a soft link of the `src` folder to `$ANTELOPE/`. Another way to get `contrib` codes is to run: `git clone https://github.com/antelopeusersgroup/antelope_contrib.git src`

From our experiences, change the ownership of the `$ANTELOPE` directory to be you, instead of the root user, if this is the case. After downloading/updating the `contrib` codes, please follow the instructions in `README.md` to compile the codes.

### 2.1 Operation Systems

This program has been fully tested under Mac OSX Mountain Lion (10.8), Mavericks (10.9), Yosemite (10.10), and Sierra (10.12). Newer Mac OS (e.g., High Sierra) should be working but without heavy tests. For other linux-based systems, it should be working but please report any issues at: <https://github.com/xyangpsp/RFeditor>.

### 2.2 Library dependency

The following libraries are required in order to compile RFeditor (current version 3.x). You may need to install these libraries by the order as shown here:

#### (1) X11

On MacOS, the library was part of the XQuartz package. The latest test in July 2018 was built against XQuartz 2.7.11.

#### (2) boost (<http://www.boost.org>):

This is a C++ library. On Mac OSX, you can install it from fink. From our experience, please install the version tagged as “nophython”.

```
$fink list boost
$fink install boostpackagename
```

#### (3) xmotif: xwindow libraries;

```
$fink list motif
$fink install motifpackagename
```

In addition to fink installation, xmotif libs (e.g., libXm.a) are required. The package can be installed manually from source code. **The version installed using fink doesn't include libXm.a.** This package/source code could be downloaded from: <http://motif.ics.com> and the link there.

The latest release is motif-2.3.8, available on sourceforge.net (accessed July 2018). The installation process is straightforward as documented in the downloaded motif-x.x.x package.

#### << Trouble shooting in installing motif-2.3.8>>

You may need to install freetype2 libraries for font types. They can be installed using fink. If you get errors when installing motif, check the content in Makefile to make sure the libraries are pointing to the right directory. If not, try the following way to run configure:

```
./configure CFLAGS='-I/sw/include -I/sw/include/freetype2 -I/opt/X11/include' CPPFLAGS='-I/opt/X11/include -I/sw/include'
FREETYPE_CFLAGS='-I/sw/include/freetype2' FONTCONFIG_CFLAGS='-I/sw/include'
FONTCONFIG_LIBS='-L/sw/lib -lfontconfig'
FREETYPE_CFLAGS='-I/sw/include/freetype2'
```

#### <<< Configure Antelope localmake for boost and xmotif >>>

After successfully installed boost and xmotif libraries, you have to enable boost and xmotif for Antelope. This can be done by running in any terminal:

```
$localmake_config
```

This will lead you to the interface where you can enable BOOST and XMOTIF capabilities. You will need to type the paths for LIB and INCLUDE for both BOOST and XMOTIF libraries and then: “File->Save and Quit” to save these configurations. For XMOTIF, if your fink directory is /sw, then the INCLUDE and LIB directories are: /sw/include and /sw/lib, respectively.

#### (4) libseispp (\$ANTELOPE/src/lib/seismic/libseispp):

Note: under Antelope 5.8, seems now() function cannot be found. Commented out Makefile under libseispp for ArrivalUpdater.o in OBJS.

This library is released along with the Antelope contrib package. Once you successfully compiled contrib software, libseispp should be already available. If not, cd to this directory and type:

```
$make Include
$make
```

#### (5) libseisw (\$ANTELOPE/src/lib/graphics/seisw):

Seismic widget library for plotting seismic traces as wiggles. It is part of the Antelope contrib package. Once you successfully compiled contrib software, libseisw should be already available. If not, cd to this directory and type:

```
$make Include
$make
```

With the latest release (RFeditor v3.7.4), we added the source code for the required library libseisw.a under libseisw. When you compile RFeditor in the next step, this library will be automatically installed.

### 2.3 Install *RFeditor*

NOTE: In antelope 5.8 and later, antelope programs use TOOLCHAIN macro to define the compiler libraries. For now, *RFeditor* doesn't work under the antelope toolchain for OSX. Fix this issue by setting environment variable in ~/.bash\_profile (or similar other files):

```
export TOOLCHAIN=native
```

Then:

```
$source ~/.bash_profile
```

Once you have all of the required libraries installed and properly configured, cd to \$RFEROOT and type in command line:

```
$make Include
```

```
$make
```

If the above compiling procedure is successful, run:

```
$make install
```

This deposit tredit, wfprocess, and decon tables to \$ANTELOPE/contrib/data/css3.0.ext/, deposit *RFeditor* executable to \$ANTELOPE/contrib/bin, and deposit *RFeditor*.pf to \$ANTELOPE/contrib/data/pf/. **wfprocess** table was first released with **dbxcor**. We include it **here for convenience since some of the editing procedure open database with wfprocess table**. Please make sure you have the permission to write, read, and execute programs!

If you the above compiling went through, congratulations, *RFeditor* is available to you.

#### <<< Trouble Shooting >>>

If you get errors complaining that some libraries are not found, you may need to find the library and copy it (or create a symbolic link) to: \$ANTELOPE/lib. For example, **lseispp** means library file **libseispp.a**.

### 3. Command Line Options

You can start RFeditor from the terminal by simply typing the program name: RFeditor. This will give you a brief usage information. For example:

```
$RFeditor
< version v3.7.4 > 7/22/2018
RFeditor dbin dbout [-d outdir] [-tredit filename] [-rm] [-go] [-continue] [-fa fa_filename] [-pf pffile] [-laststa xx] [-ss subset_condition] [-v|V] [-h|H]
** Use -h to print out detailed explanations on the options.
```

Xiaotao Yang & Gary Pavlis, Indiana University

However, to start the program on an Antelope database, it requires two arguments: the input database and the output database, where the edited data will be stored.

- d outdir: directory saving the output data;
- tredit filename: the editing summary will be saved into a plain text file with the name of filename. By default (without this option), the program only saves edit summary to Antelope table "tredit";
- rm: turn on review mode. Under review mode, edits will NOT be saved. In this case, type dash (-) as the outdb name;
- go: GUI-off mode. This is designed for automated QC of large dataset;
- continue: turn on continue mode. When this option is used, the program automatically continues onto the next station after the last station in the existing outdb. The program checks tredit table for the last working station;
- fa fa\_filename: the program will save first arrival (first peak) information into the plain text file specified by fa\_filename;
- pf pffile: parameter file. By default, the pffile is: \$PFPATH/RFeditor.pf in the current working directory. \$PFPATH is specified by the Antelope environment.
- laststa xx: jump to the station after xx;
- ss subset\_condition: apply subset condition to the database before editing;
- v|V: run program in verbose mode;
- h|H: get help information on command options and version history.

*RFeditor* has two running modes: interactive mode with Graphical User Interface (GUI-mode) and automated mode (Auto-mode). GUI-mode allows the user to interactively work on each station gather, select quality control procedures and customize parameters for each metric. For a large dataset, we recommend this mode for testing parameters before running in Auto-mode.

By default, the program starts in GUI-mode. To run the program in Auto-mode, use option: `--gui-off` or `-go`.

## 4. Parameter File

In addition to RFeditor.pf or other name for RFeditor parameter file, there is a very important PF file: **seispp\_attribute\_maps.pf**. This PF file is required, as it tells the program how to find tables and attributes that are not standard antelope built-in CSS3.0 attributes. This file also contains aliases of different attributes.

The following are main parameters driving the program (see RFeditor.pf in RFEROOT for example parameter values).

### 4.1 Global parameters driving the program

#### minimum\_number\_receiver\_functions

Stations with number of events less than this will be skipped automatically with a log message.

#### FA\_reference\_time

First arrival time shift for plot (default displays First Arrival at time 0). Signs: +, shift to positive time axis; -, shift left to negative time axis. When **use\_arrival\_data** is set to false, this is the FA time in the data and the trace will be plotted starting from 0 seconds.

#### use\_arrival\_data

This is a Boolean parameter (true/false). If this is true, the arrival and assoc tables must be provided and will be used in converting the time frame from absolute to relative.

#### use\_decon\_in\_editing

This is a Boolean parameter (true/false). If this is true, the decon table must be provided. This table is generated by the program associated with the Generalized Iterative Deconvolution method by Wang and Pavlis (2016). When this parameter is set to true, the QC process will enable deconvolution attributes related procedures.

#### use\_netmag\_table true

This is a Boolean parameter (true/false). If this is true, the netmag table must be provided. The program will read in magnitude information from this table. Currently, magnitude information can be used in sorting the receiver functions (a station gather).

#### radial\_channel\_key

#### transverse\_channel\_key

#### vertical\_channel\_key

The above three parameters are channel codes for the three component of the receiver function.

#### no\_vertical\_data

This is a Boolean parameter (true/false). If this is true, the program will only process radial and transverse data. If your data includes vertical data, this parameter is not required. The default value is false. The program only tries to read this parameter after it fails to read the **vertical\_channel\_key** from the parameter file.

#### edit\_on\_channel



This parameter (radial, transverse, or vertical) gives the option to choose which component to edit.

#### `use_wfdisc_in`

This is a Boolean parameter (true/false). If this is true, the program will read waveform data following wfdisc table. Otherwise, wfprocess table is used.

#### `apply_prefilter`

This is a Boolean parameter (true/false). If this is true, the receiver function data will be filtered before processing and plotting (in GUI-mode). We recommend turn the prefilter on for pure-spike RF data. Otherwise, QC processing will not be working correctly.

#### `wavelet_type`

Available types: filter, gaussian, ricker. Ricker wavelet should NOT be used for the purpose of QC.

#### `filter`

Only if `wavelet_type` is filter, the filter parameters should be specified here. For example, a Butterworth band-pass filter with 2 poles: BW 0.2 2 2 2. Ignore this parameter if the `wavelet_type` is set to gaussian or ricker.

#### `data_sample_interval`

#### `wavelet_width_parameter`

#### `wavelet_length`

#### `wavelet_normalization_method`

The above four parameters are needed by gaussian or ricker `wavelet_type`. These are ignored if the `wavelet_type` is filter. The `data_sample_interval` is the sample interval in time domain, e.g., 0.025. The `wavelet_width_parameter` is the width of the wavelet. It is the sigma for Gaussian wavelet and the central frequency for Ricker wavelet. The `wavelet_length` is length of the wavelet. We suggest that the wavelet is at least 3 times the width parameter in time domain. `wavelet_normalization_method` is recommended to be PEAK.

#### `save_wfdisc_table`

This is a Boolean parameter (true/false). If this is true, when reading input from wfprocess table, a wfdisc table will be generated containing the receiver functions after QC. The program will use channel keys define above for different channels. This parameter will be ignored if reading input waveform from wfdisc (i.e., `use_wfdisc_in` is true). If `use_wfdisc_in` is false and this parameter is true, then the program saves the output to both wfdisc and wfprocess tables.

#### `save_wfprocess_table`

This is a Boolean parameter (true/false). If this is true, when reading input from wfdisc table, a wfprocess table will be generated containing the receiver functions after QC. This parameter will be ignored if reading input waveform from wfprocess (i.e., `use_wfdisc_in` is false), when wfprocess table will be saved by default.

#### `save_3C_data`

This is a Boolean parameter (true/false). It is applicable only if the input is from wfprocess table and with 3c datatype, which means that each row in wfprocess table is a three-component seismogram. If this is true, the waveforms after QC will be saved in 3c datatype. datatype is an entry of the wfprocess and wfdisc table.

#### save\_decon\_table

This is a Boolean parameter (true/false). When this is true, the decon table will be saved after QC. However, ONLY one component of the decon table will be saved. This component is specified by edit\_on\_channel and the associated channel key will be used in saving the table. This parameter will be ignored if use\_decon\_in\_editing is false.

#### save\_vertical\_channel

This is a Boolean parameter (true/false). When it is true, vertical component of the three component seismogram will be saved after QC. This is automatically set to true if the input datatype is 3c (i.e., ThreeComponentSeismogram). We use this parameter because there are some imaging programs that only use radial and transverse components.

#### save\_metadata\_only

This is a Boolean parameter (true/false). When it is true, the program only saves database tables but not the real waveform data. This works for the case when the same type of input and out tables are used. For example, both use\_wfdisc\_in and save\_wfdisc\_table are true. When use\_wfdisc\_in is false, which means use wfprocess as input table, the datatype is 3c, and save\_wfdisc\_table is true, the program currently is unable to handle this combination and will throw errors and exist.

#### save\_filtered\_data

The user could choose to save the filtered data by tuning this on (or set to true). If this is true, the data after QC will be filtered before saving using the filter defined above by apply\_prefilter and other related parameters.

#### output\_dfile\_base

Base of the output data file name, e.g., RFedited. The file will be named as: RFedited\_KF28.R for radial, \*.T for transverse, and \*.Z for vertical. When saving 3C data, the file extension will be \*.3C for wfprocess table, and \*.w for wfdisc table.

## 4.2 Parameters driving the QC in GUI-mode

The parameter array, gui\_edit\_parameters &Arr{}, contains all of the parameters used by GUI-mode RFeditor.

```
#stacking window params for robustSNR stacking.
#stacktype RobustSNR
robust_window_start -1
robust_window_end 10
```

```
NFA_tolerance_TW_start -2
NFA_tolerance_TW_end 5
PCoda_search_TW_start 5
PCoda_search_TW_end 35.0
PCoda_grow_tolerance 0.0
max_trace_abs_amplitude 100 #true amplitude (as stored in the data).
CodaCA_search_TW_start 2.0
CodaCA_search_TW_end 20.0
CodaCA_tolerance_twin_length 5 #recommend: 5*(filter width in time-domain).
RefXcor_search_TW_start -1
RefXcor_search_TW_end 10
```

#decon parameter threshold: default values.

```
niteration_min 20
niteration_max 1000
nspike_min 20
nspike_max 1000
epsilon_min 0.0
epsilon_max 50.0
peakamp_min 0.001
peakamp_max 1
averamp_min 0.0
averamp_max 1
rawsnr_min 1
rawsnr_max 1000
```

#### 4.3 Parameters driving the QC in Auto-mode

```
apply_klat false
apply_decon_ALL true # if true, apply all procedures based on cutoffs of deconvolution
#parameters. Set to false if only some of the procedures are
#needed.
```

```
apply_kdnitn false
apply_kdnspike false
apply_kdepsilon false
apply_kdpkamp false
apply_kdavamp false
apply_kdsnr false
apply_kldsi true
```

```
apply_knfa true
apply_kgpc true
apply_kca true
```

apply\_klsw true  
 apply\_klxcor true  
 apply\_klrfqi true

apply\_kdnitn  
 apply\_kdnspike  
 apply\_kdepsilon  
 apply\_kdpkamp  
 apply\_kdavamp  
 apply\_kdsnr  
 apply\_kldsi

*Table 4.1. The order of quality control procedures under Auto-mode and corresponding procedure names in the parameter file. See Yang et al. (2016) for details of the procedures.*

Order	Procedure	Name in parameter file	Category
1	Cutoff of the number of iterations	<i>apply_kdnitn</i>	<i>Decon-Procedures</i>
2	Cutoff of the number of spikes	<i>apply_kdnspike</i>	
3	Cutoff of epsilon (the ratio of residual energy to original energy)	<i>apply_kdepsilon</i>	
4	Cutoff of the maximum (peak) amplitude	<i>apply_kdpkamp</i>	
5	Cutoff of the average amplitude	<i>apply_kdavamp</i>	
6	Cutoff of the SNR of the original seismogram	<i>apply_kdsnr</i>	
7	Cutoff of the Deconvolution Success Index	<i>apply_kldsi</i>	
8	Discard Type-4 (negative first arrivals) traces	<i>apply_knfa</i>	<i>Trace-Procedures</i>
9	Discard Type-5 (growing <i>P</i> -coda) traces	<i>apply_kgpc</i>	
10	Discard Type-6 (clustered <i>P</i> -coda) traces	<i>apply_kca</i>	
11	Cutoff of the Robust stack weight	<i>apply_klsw</i>	<i>Stat-Procedures</i>
12	Cutoff of the correlation coefficient with reference trace	<i>apply_klxcor</i>	
13	Cutoff of the Receiver Function Quality Index	<i>apply_klrfqi</i>	

NFA\_tolerance\_TW\_start -2  
 NFA\_tolerance\_TW\_end 5  
 PCoda\_search\_TW\_start 5.0  
 PCoda\_search\_TW\_end 35.0  
 CodaCA\_search\_TW\_start 2.0  
 CodaCA\_search\_TW\_end 20.0  
 RefXcor\_search\_TW\_start -1  
 RefXcor\_search\_TW\_end 10  
 max\_trace\_abs\_amplitude 100

#This is the threshold for maximum true amplitude (as stored in the data).

CodaCA\_tolerance\_twin\_length 5  
 PCoda\_grow\_tolerance 0.0  
 RFQI\_weigth\_stackweight 0.2  
 RFQI\_weigth\_refxcorcoe 0.3  
 RFQI\_weigth\_successindex 0.5  
 rfqi\_min 0.6

niteration\_min 20  
 niteration\_max 1000  
 nspike\_min 20  
 nspike\_max 1000  
 epsilon\_min 0.0  
 epsilon\_max 50.0  
 peakamp\_min 0.001  
 peakamp\_max 1  
 averamp\_min 0.0  
 averamp\_max 1  
 rawsnr\_min 1  
 rawsnr\_max 1000

stackweight\_min 0.2  
 xcorcoe\_min 0.5  
 dsi\_min 0.3  
 stacktype RobustSNR  
 robust\_window\_start -1  
 robust\_window\_end 10

## 4.4 Other optional parameters

### 4.4.1 First arrival detection

First Arrival (FA) detection parameters are not required if FA detection is not turned on. Use -fa option when running RFeditor to turn it on. Here we list these parameters and the default values. The user can change the default values by specifying new values in the parameter file.

**FA\_sensitivity 10e-4**

This is the sensitivity in amplitude: turn on detection only if the amplitude is above this value. this is used in TraceEditOperator object.

**FA\_detect\_length 0.8**

**FA\_search\_TW\_start -5**

**FA\_search\_TW\_end 5**

Time window length for FA detection. The program will only detect FA within this window specified by the start and end time stamps. When detecting FAs, the moving window length is specified the the FA\_detect\_length parameter above. The program searches for FA within this length after first non-zero values

( $\geq$ FA\_sensitivity). The empirical length value for reference:  $\geq 4 \times \text{gaussian\_sigma}$  for gaussian or  $1.5 \times \text{ricker\_side\_lope\_distance}$  for ricker.

**data\_shaping\_wavelet\_type GAUSSIAN**

This is referenced only when detecting the first arrivals. This is the wavelet type used to generate the receiver functions, which is input of the RFeditor program. Use RICKER if ricker was used in either deconvolution or the pre-filtering process. There are three available types: SPIKE, GAUSSIAN, RICKER (CASE SENSITIVE). This parameter is read-in just once when the TraceEditOperator object is initiated.

#### 4.4.2 Metadata lists for input and output tables

In parameter file, metadata lists are specified by a table of metadata tags/attributes and metadata types. **In the current version of RFeditor, it uses built-in metadata lists unless the user specifies them in the parameter file.**

**mdlist\_ensemble**

Metadata list read in for each time series ensemble (station gather).

**mdlist\_wfdisc\_in**

Metadata list read in for each receiver function trace when using wfdisc table as input.

**mdlist\_wfdisc\_out**

Metadata list of the output wfdisc table.

**mdlist\_wfprocess\_in**

Metadata list read in for each receiver function trace when using wfprocess table as input. Adjust the lists of attributes when using decon table, arrival data or netmag table.

**mdlist\_wfprocess\_out**

Metadata list of the output wfprocess table.

#### 4.4.3 Keys of the deconvolution attributes

The following are default values for decon keys. If you want to use other values, please make sure they are consistent with those in the mdlist\_wfprocess\_in metadata list/table when use\_decon\_in\_editing is true. Those are defined in the parameter arrays, gui\_edit\_parameters &Arr{} and auto\_edit\_parameters &Arr{}.

Defaults definitions:

decon\_nspike\_key decon.nspike

decon\_rawsnr\_key decon.rawsnr

decon\_averamp\_key decon.averamp

decon\_epsilon\_key decon.epsilon

decon\_niteration\_key decon.niteration

decon\_peakamp\_key decon.peakamp

#### 4.4.4 Plotting window parameters

Parameters for the plotting window shown here are the built-in default values. **PLEASE DO NOT change them unless necessary!** You can specify the values for these parameters in the parameter array, gui\_edit\_parameters &Arr{}. Here are list the default values for all

of these parameters. These values are default values built-in in the program. Only add parameters that you want to change.

```
SUVariableArea_grey_value 1
VariableArea true
WiggleTrace true
blabel Data Window
blabel2 Data Window
clip_data true
clip_percent 99.5
clip_wiggle_traces false
d1num 0.0
d2num 0.0
default_curve_color black
editing_mode single_trace
f1num 0.0
f2num 0.0
first_trace_offset 0.0
grid1 1
grid2 1
gridcolor blue
hbox 850
wbox 950
interpolate true
label1 time
label2 index
labelcolor blue
labelfont Rom14
labelsize 18.0
n1tic 5
n2tic 1
plot_file_name SeismicPlot.ps
style normal
time_axis_grid_type solid
time_scaling auto
title Receiver Function Data
titlecolor red
titlefont Rom22
titlesize 36.0
trace_axis_attribute assoc.delta
trace_axis_grid_type none
trace_axis_scaling auto
trace_spacing 1.0
trim_gap_edges true
use_variable_trace_spacing false
verbose true
windowtitle RFeditor
x1beg 0.0
x1end 120.0
x2beg 0.0
```

```
x2end    24.0
xbox50
xcur1.0
ybox50
beam_hbox 250
beam_clip_data false
beam_trace_spacing 1.0
beam_xcur 1.0
beam_trace_axis_scaling auto
```



## 5. Data Preparation

The waveforms (receiver functions) need to be saved in Antelope Datascope Database format using either wfdisc table or wfprocess table for indexing.

### 5.1 Data for deconvolution

Details on this step should be covered in deconvolution programs. We use `trace_decon` by Wang and Pavlis (2016) based on generalized iterative deconvolution. `trace_decon` saves deconvolution attributes that can be used in QC using RFeditor. The code for `trace_decon` can be obtained through contacting Yinzhi Wang at Indiana University. See Wang and Pavlis (2016) for details on the method. The steps to get receiver functions can be summarized as:

- 1) Download waveform, either continuous or by earthquakes. Using `miniseed2db` to generate the `wfdisc` table.
- 2) If step 1) downloaded continuous waveforms, we need to build a teleseismic catalog here.
- 3) Generate predicted arrivals. `trace_decon` doesn't have to use hand-picked arrivals. We used predicted arrivals:  
`get_predicted_Parrivals catalog_db station_db outdb`

Then, run:

```
dbassoc_arrival -p 2 arrival_db origin_db
```

run: `simple_evid_set` (included in **Utilities**) to correct inconsistency of event table and origin table. Basically, this table use the new `orid` generated by `dbassoc_arrival` to replace the `evid` and `prefor` and generates a new event table.

- 4) Link the `wfdisc` table to the catalog data base tables. Check the final data base to make sure the waveforms are correctly linked.
- 5) Run `trace_decon`.
- 6) We call the resultant receiver functions database as: `datadb`.

### 5.2 Prepare for QC using RFeditor

Due to data gaps, in the receiver function db, i.e., `datadb`, there might be traces with only very few samples. Make sure exclude very short traces from the db. When getting errors, such as “**stacking window outside the data window**”, you need to come back to this step and clean up short traces.

## 6. QC in GUI-Mode

Use the data in this release package for testing purpose. Unzip the file: RFeditor\_demo\_portable.zip. cd to the directory and following the instructions in README.txt to test the program and the instructions in this section and the next one.

GUI-mode is designed to let the user manually check the data quality and determine the optimized quality control parameters. Once the parameters are determined after working through 20-50 stations, they can be set in the parameter file, e.g., RFeditor.pf, for GUI-off mode. In RFeditor.pf, there are some GUI QC (Quality Control) parameters set as default values. All of those values and other unset parameters could be customized in GUI. **Specifically, as documented in Yang et al. (2016), we suggest the user conduct QC processing using RFeditor following the workflow below:**

*Step 1.* Test for appropriate filter or wavelet parameters used in viewing and editing the receiver functions;

*Step 2.* Set default GUI-mode parameters for QC procedures. The user may change these parameters later in GUI-mode;

*Step 3.* Start *RFeditor* under GUI-mode to test QC procedures and optimize parameters.

(a) Apply individual editing procedures under <Edit>. Examine the data as station gathers sorted by the attribute of interest (options in <Sort> menu) and then choose a cutoff based on this visual inspection. Exclude killed traces under <View> (shortcut: X).

(b) Inspect the data discarded by selected procedures under *View -> Review Killed Traces*. Check trace metadata to see the procedure that killed that trace under *View -> Show Trace Metadata -> For Picked Trace* (shortcut: M).

(c) Adjust parameters until the remaining station gather look clean and little to no good data are discarded.

(d) Repeat (b) to (c) for combinations of multiple QC procedures.

(e) Repeat (a) to (d) as needed for other station gathers to finalize QC procedures and parameters for Auto-mode. We have found that a sample of around 10 to 15 station gathers is sufficient to define a reasonable cutoff for most parameters.

*Step 4.* Run *RFeditor* under Auto-mode to process all station gathers based on the parameters determined from *Step 3*.

*Step 5.* Examine samples of station gather after QC under GUI-mode.

*Step 6.* Repeat Steps 1 to 5 as needed to adjust QC procedures and parameters.

To denote the percentage of receiver functions left after quality control (Yang et al., 2016), we define the Acceptance Rate (AR),  $\gamma$ , of applying QC on receiver functions as:

$$\gamma = \frac{R'}{R} \times 100, \quad (6.1)$$

where  $R$  is the number of seismograms in the data set before editing,  $R'$  is the number of seismograms after applying the selected QC procedures. We use the factor of 100 to make  $\gamma$  a percentage measure. *RFeditor* computes the average  $\gamma$  for each station gather. For every example shown below, we estimated the average  $\gamma$  for the whole receiver function data set.

## 6.1 Mouse operation conventions

In RFeditor, when selecting traces, please click middle-button of the mouse. Use left click as normal. Left-click, hold, and drag will zoom in on the selected area. Left-click again to go back to the original view after zooming in. The method that RFeditor uses to change parameter values is through clicking certain menus in GUI and, when inquired by the program, typing values in the terminal window, following the hints.

## 6.2 Menus in the tool bar

Figure 6.1 is a screenshot of a typical RFeditor window after opening. Red title shows the channel code and the station name. In the Data Window, the positive lobes are filled in black. X-axis shows the time in seconds after first P, or from the beginning, depending on the definition of first arrival in RFeditor.pf. Y-axis is the order of the traces in the current view.




Figure 6.1 A typical GUI window displaying the waveform traces. The traces, by default, are sorted by event ID. The order can be changed when sorting with different attributes.

### 1) File

Currently, there are three functions (Figure 6.2): save picked trace, save edits and go next (edits are not saved under review mode with argument: -rm when starting the program), and quit the program without saving the QC result for the current station. On the right of each option is the keyboard shortcut, such as the Ctrl+Q to quit the program.

There are multiple options that you choose to save trace or all traces. From the submenu, you can save the picked trace (Pick A Trace), all traces in the current view (All Traces), the stack trace using Robust stack algorithm by Pavlis and Vernon (2010) (Robust Stack Trace),

or the stack trace by simply averaging all traces in the current view (Average Stack Trace). The trace is saved as plain text file. There is a MATLAB script under `$RFEROOT/Utilities/readrf.m` that can be used to read the saved trace data.

By default, the program saves trace metadata following version code=2. This can be changed by click: File -> <Save Trace To File> -> <Choose Metadata Version>. **This choice will overwrite the default [2] for future stations, until changed again.** There are currently three versions supported:




Figure 6.2 <File> menu.

Choose metadata version code for saved trace from below (1, 2, 3):

1 - Example below (basic version)

%Metadata version 1

```
station      : BLO
start_time   : 4/01/2014 23:56:30.025
evid         : 1169
samples      : 6001
dt           : 0.025000
t0           : -29.987570
stack_weight : -9999.0000
RT_xcorcoe   : -9999.0000
RFQualityIndex : -9999.0000
DeconSuccessIndex : 0.4620
niteration    : 3
nspike       : 2
epsilon      : 30.69890
peakamp      : 0.40356
averamp      : 0.00535
rawsnr       : 2.50000
```

2 - Example below (basic+magnitude)

%Metadata version 2

```
station      : BLO
start_time   : 4/01/2014 23:56:30.025
evid         : 1169
magnitude    : -9999.00
```

```

magtype      :-
samples      : 6001
dt           : 0.025000
t0           : -29.987570
stack_weight : -9999.0000
RT_xcorcoe   : -9999.0000
RFQualityIndex : -9999.0000
DeconSuccessIndex : 0.4620
niteration    : 3
nspike       : 2
epsilon      : 30.69890
peakamp      : 0.40356
averamp      : 0.00535
rawsnr       : 2.50000

```

### 3 - Example below (basic+magnitude+back\_azimuth)

```

%Metadata version 3
station      : BLO
start_time   : 4/01/2014 23:56:30.025
evid         : 1169
magnitude    : -9999.00
magtype      :-
back_azimuth : 172.5
samples      : 6001
dt           : 0.025000
t0           : -29.987570
stack_weight : -9999.0000
RT_xcorcoe   : -9999.0000
RFQualityIndex : -9999.0000
DeconSuccessIndex : 0.4620
niteration    : 3
nspike       : 2
epsilon      : 30.69890
peakamp      : 0.40356
averamp      : 0.00535
rawsnr       : 2.50000

```

## 2) Edit

All QC procedures and parameters are built in <Edit> menu, as shown in Figure 6.3. For options with a symbol of right-pointed triangle, there are sub-menus for additional QC options.

**Undo Auto-Edits:** This option can restore the traces killed by the LAST (only once) auto-editing procedure.

**Manual-Editing Modes:** Single Trace Edit mode lets you kill one trace at a time by picking the trace using middle button of the mouse. Cutoff Edit Mode allows you kill all trace below the picked trace on the screen. This is useful after sorting by certain attributes in <Sort>. You can

reverse the trace order (Sort -> <Reverse Trace Order>) in case the bad traces are top of the sorted traces.

<Restore Ensemble>: This option allows you to restore all original traces before any editing for the current station.

Users are recommended to explore auto-editing procedures using the demo data package.

Table 6.1 lists a few shortcuts for quick QC:




Figure 6.3 <Edit> menu.

Table 6.1 Key shortcuts.

Shortcut	Action	Category
Ctrl+T	Pick a trace and save it to a text file.	File
G	Save edits for current station (not under review mode) and go to next station.	
A	Apply all procedures based on trace characteristics.	Edit
D	Apply all procedures based on cutoffs of deconvolution parameters from trace_decon.	
I	Manually kill selected traces, one trace at a time	
O	Manually kill traces below the picked trace in the current screen view	
W	Sort the traces by robust-stack weight	Sort
R	Sort the traces by cross-correlation coefficient with picked reference trace	
C	Compute decon-success index, defined in Yang et al. (2016)	
L	Compute receiver function quality index, defined in Yang et al. (2016)	
X	Exclude killed traces from the current screen view	View

### 3) View

This menu includes, plot traces, view trace metadata, and review killed traces. Amongst these options, Exclude Killed Traces (shortcut: X) is useful to clean up the screen by only displaying the traces left after killing bad traces. Show Trace Metadata (shortcut: M) allows you to check

the trace information. When under the mode of Review Killed Traces, the metadata for killed traces will show name of the procedure that this trace is killed by.




Figure 6.4 <View> menu.

#### 4) Sort

This menu includes mainly the sorting methods. After applying any sorting method, click <Print Trace Order> to display the event ID and order of the traces in the terminal window.




Figure 6.5 <Sort> menu.

#### 5) Tools

Click <Statistics> to print a summary of the current station, for example:

```
Total number of kills: 0>
--- Statistics from TraceEditPlot ---
Working on station      BL0
Number of kills         0
Traces in current view  131
Traces in original data 131
Auto-killed traces      0
Manual-killed traces    0
Traces left             131
Acceptance Rate (%)     100

----- End of statistical data -----
```

The option <Compute Decon-Attributes> is under-development and will be implemented in future releases.




Figure 6.6 <Tools> menu.

6) Help

Print help message about major shortcuts and usage information.



## 7. QC in Auto-Mode

For a large dataset, testing parameters in GUI-mode, Auto-mode is recommended to finish the QC process. In the Auto-mode, readers need to be aware of the order that QC procedures are implemented in *RFeditor*, as shown in Table 4.1.

## References

Wang, Y. Z., and G. L. Pavlis (2016), Generalized iterative deconvolution for receiver function estimation, *Geophys. J. Int.*, 204(2), 1086-1099, doi:10.1093/gji/ggv503.

Yang, X. T., G. L. Pavlis, and Y. Wang (2016), A quality control method for teleseismic P-wave receiver functions, *Bull. Seismol. Soc. Am.*, 106(5), 1948–1962, doi:10.1785/0120150347.

Pavlis, G. L., and F. L. Vernon (2010). Array processing of teleseismic body waves with the USArray, *Comput. Geosci.* **36** 910-920.